



Absolute Medical. 1843 W Hubbard St #2A
Chicago, IL 60622
Tel: 312 233 2207 Fax: 866 860 9358
To Order Online: orders@absolutemedical.com
Our website: absolutemedical.com

Patient Last Name: _____ Patient First Name: _____
Fitter Last Name: _____ Fitter First Name: _____
Date: _____

ARMASSIST CUSTOM

Product Information

Size

☐ CUSTOM

Arm

☐ LEFT ☐ RIGHT

Length (see Measurement D below)

- ☐ I have read and understand the written measuring instructions for the ARMASSIST™ CUSTOM
- ☐ I have signed and attached the "Custom Order Terms & Conditions" form
- ☐ I have emailed digital photos to: orders@absolutemedical.net

ARM

☐ LEFT
☐ RIGHT

FOAM

☐ FLAT FOAM
☐ WAVEFOAM™

CUSTOM SIZE

Excellent choice for patients who are outside of standard size ranges.
Custom length available.

CIRCUMFERENCE MEASUREMENTS

_____ cm _____

25 cm _____

20 cm _____

15 cm _____

10 cm _____

5 cm _____

Ø POINT _____

5 cm _____

10 cm _____

15 cm _____

20 cm _____

25 cm _____

_____ cm _____

A LENGTH

B LENGTH

C LENGTH

D LENGTH

E WIDTH

Width of hand across dorsal Metacarpal Heads

ARMASSIST CUSTOM



IMPORTANT

Before taking measurements, please complete the following:

SUPPLIES NEEDED:

1. *All measurements must be taken in a straight line, unless otherwise specified, with the tape measure following the contours of the limb. Do not pull the tape tight; hold it lightly against the skin.*
2. *Encircle arm with tape measure located as high as possible at Axilla. Mark on the proximal edge of tape at the Anterior, Dorsal, and Posterior aspects of arm, and record the circumference on the line labeled Posterior Axilla.*
3. *Encircle elbow with the proximal edge of a tape measure aligned at the elbow crease and Olecranon Process (elbow). Mark the dorsal aspect of the elbow along this edge, and record the circumference on the line labeled Elbow (0 Point).*
4. *Encircle wrist with the distal edge of a tape measure aligned with the ulnar styloid process. Mark the dorsal aspect of the wrist along this edge, and record the circumference on the line labeled Ulnar Styloid.*

INSTRUCTIONS CUSTOM ARMASSIST:

**All measurements should be recorded in centimeters. Apply slight tension to hold the tape measure in place.*

STEP 1: Locate circumference measurement position

Starting with "0" of the tape measure at your mark on the dorsal aspect of the elbow, mark the dorsal aspect of the upper arm in 5cm increments up to the mark made from the Posterior Axilla on the dorsal aspect of the arm.

Starting with the "0" of the tape measure at your mark on the dorsal aspect of the elbow, mark the dorsal aspect of the forearm in 5cm increments down to the mark made for the Ulnar Styloid on the dorsal aspect of the arm.

STEP 2: Measure lengths

Measure upper arm from anterior axilla (inside armpit) to the elbow crease and record length in box marked Length A. Measure upper arm from posterior axilla (outside armpit) to the Olecranon Process (elbow) and record length in box marked Length B.

STEP 3: Measure lengths cont.

Measure the forearm along dorsal aspect from elbow (as marked at the mid-point between Olecranon Process and elbow crease) to the Ulnar Styloid as indicated on diagram and record length in box marked Length C. Measure hand from your mark on dorsal aspect of wrist to the third metacarpal head and record length in box marked Length D. Measure width of hand across dorsal metacarpal heads and record width in box marked E Width.

STEP 4: Measure circumferences .

Encircle arm with a tape measure at each mark located between the elbow and axilla, and record each circumference on the line corresponding to each position. Encircle arm with a tape measure at each mark located between the elbow and Ulnar Styloid, and record each circumference on the line corresponding to each position.

NOTES - Custom Arm Assist is available in: 7099-AR FlatFoam, 7199-AR WaveFoam, 7299-AR Super FlatFoam, 7399-AR Super WaveFoam.