



Absolute Medical. 1843 W Hubbard St #2A  
Chicago, IL 60622  
Tel: 312 233 2207 Fax: 866 860 9358  
To Order Online: [orders@absolutemedical.com](mailto:orders@absolutemedical.com)  
Our website: [absolutemedical.com](http://absolutemedical.com)

Patient Last Name: \_\_\_\_\_ Patient First Name: \_\_\_\_\_  
Fitter Last Name: \_\_\_\_\_ Fitter First Name: \_\_\_\_\_  
Date: \_\_\_\_\_

## LEGASSIST BELOW KNEE CUSTOM

### Product Information

- ☐ I have read and understand the written measuring instructions for the LEGASSIST™ BK CUSTOM
- ☐ I have signed and attached the "Custom Order Terms & Conditions" form
- ☐ I have emailed digital photos to: [us\\_orders@sigvaris.com](mailto:us_orders@sigvaris.com).

LEG	FOAM	FOOT OPTIONS	SIZE*	*NOTE
<input type="checkbox"/> LEFT	<input type="checkbox"/> FLAT FOAM	<input type="checkbox"/> COMPREBOOT™ PLUS (included)	<input type="checkbox"/> REGULAR	If the greatest circumference measurement is >60cm, order a Super
<input type="checkbox"/> RIGHT	<input type="checkbox"/> WAVEFOAM™	<input type="checkbox"/> CUSTOM MEDABOOT™ (additional charge)	<input type="checkbox"/> SUPER	

**CIRCUMFERENCE MEASUREMENTS**

\_\_\_\_\_ cm \_\_\_\_\_

40 cm \_\_\_\_\_ (If req'd)

35 cm \_\_\_\_\_

30 cm \_\_\_\_\_

25 cm \_\_\_\_\_

20 cm \_\_\_\_\_

15 cm \_\_\_\_\_

10 cm \_\_\_\_\_

5 cm \_\_\_\_\_

**FOOT MEASUREMENTS**

**I** \_\_\_\_\_ circumference of ankle bend and heel

**J** \_\_\_\_\_ circumference across metatarsal heads

**K** \_\_\_\_\_ length from 1st metatarsal head to heel

**M** \_\_\_\_\_ length from 3rd metatarsal head to ankle bend

**Diagram Labels:**

- C** POSTERIOR LENGTH
- D** LATERAL LENGTH
- A** ANTERIOR LENGTH
- B** MEDIAL LENGTH
- BOTTOM OF PATELLA
- ANKLE BEND
- Ø POINT
- I**, **J**, **K**, **M** (on foot)

• = Locations measured along Lateral aspect of leg



Absolute Medical. 1843 W Hubbard St #2A  
Chicago, IL 60622  
Tel: 312 233 2207 Fax: 866 860 9358  
To Order Online: [orders@absolutemedical.com](mailto:orders@absolutemedical.com)  
Our website: [absolutemedical.com](http://absolutemedical.com)

Patient Last Name: \_\_\_\_\_ Patient First Name: \_\_\_\_\_

Fitter Last Name: \_\_\_\_\_ Fitter First Name: \_\_\_\_\_

Date: \_\_\_\_\_

## LEGASSIST BELOW KNEE CUSTOM

### IMPORTANT

Before taking measurements, please complete the following:

### SUPPLIES NEEDED:

1. All measurements must be taken in a straight line, unless otherwise specified, with the tape measure following the contours of the limb. Do not pull the tape tight; hold it lightly against the skin.
2. Encircle leg with top edge of tape measure located at the bottom of patella. Mark leg on this edge of tape at the anterior, medial, posterior and lateral aspects, and record the circumference on the line labeled Bottom of Patella.
3. Encircle leg with bottom edge of tape measure aligned with the ankle bend. Mark leg on this edge of tape at the anterior, medial, posterior and lateral aspects, and record the circumference on the line labeled Ankle Bend (0 Point).

### INSTRUCTIONS CUSTOM LEGASSIST BK:

*\*All measurements should be recorded in centimeters. Apply slight tension to hold the tape measure in place.*

### STEP 1: Locate measurement circumference positions

Starting with "0" of the tape measure at your mark on the lateral aspect of the ankle bend, mark the leg in 5cm increments up to your mark on the lateral aspect of the bottom of patella.

### STEP 2: Measure lengths

Measure leg from your mark on the anterior aspect of the ankle bend to your mark on anterior aspect of bottom of patella and record length in box marked A. Measure leg from your mark on the medial aspect of the ankle bend to your mark on medial aspect of bottom of patella and record length in box marked B. Measure leg from your mark on the posterior aspect of the ankle bend to your mark on posterior aspect of bottom of patella and record length in box marked C. Measure leg from your mark on the lateral aspect of the ankle bend to your mark on lateral aspect of bottom of patella and record length in box marked D.

### STEP 3: Measure circumferences

Encircle leg with a tape measure at each mark located between the ankle bend and bottom of patella, and record each circumference on the line corresponding to each position.

### STEP 4: Foot measurements

Measure foot from heel to 1st metatarsal head (or desired boot length) and record length in Box K. Measure Top of Foot from the 3rd metatarsal head to Ankle Bend and record length in Box M. Encircle the Ankle Bend and Heel with a tape measure and record the circumference in Box I. Encircle the foot across the metatarsal heads and record the circumference in Box J.

**NOTES - Leg Assist Below Knee is available in: 7099-BK Flat Foam, 7199-BK Wave Foam, 7299-BK Super, Flat Foam, 7399-BK Super, Wave Foam.**